

Exporting Sapphire™ 7” Touch Screen Log Files

Product: Sapphire 7” Touch Screen
(Cat. No. TS007-000/TS007-V00)

Article ID: 02032014-DB/KA-01

Date: February 3, 2014

Summary: This article describes the process for exporting log files from the Sapphire 7” Touch Screen to a USB drive.

Information:

1. Access the Administration Menu


- Press and hold Date/Time on the Sapphire Touch Screen interface to access the administration menu. Sign in using default username: administrator and the default password: 1234.

2. Export Log Files

- Insert a USB drive into the USB connection on the Sapphire Touch Screen




- Select Export Logs from the Sapphire Settings Menu




Leviton Mfg. Co., Inc. Lighting & Energy Solutions

20497 SW Teton Avenue, Tualatin, OR 97062 1-800-736-6682 Tech Line: 1-800-959-6004 Fax: 503-404-5594 www.leviton.com/les
© 2014 Leviton Manufacturing Co., Inc. All rights reserved. Subject to change without notice.

- A progress bar window will display showing the progress of the log export



- A status window will display once the export is complete. If you need to cancel the export press Cancel



- Press OK to return to the settings menu. A .zip file will be saved on the USB drive with the name Sapphire Log and the date the log was exported.

Contact: For questions or concerns, please call LES Technical Support at (800) 959-6004.